

Parallels® Virtual Automation 4.5

Installation Guide

ISBN: N/A
Parallels Holdings, Ltd.
c/o Parallels Software, Inc.
13755 Sunrise Valley Drive
Suite 600
Herndon, VA 20171
USA
Tel: +1 (703) 815 5670
Fax: +1 (703) 815 5675

Copyright © 1999-2009 Parallels Holdings, Ltd. and its affiliates. All rights reserved.

Parallels, Coherence, Parallels Transporter, Parallels Compressor, Parallels Desktop, and Parallels Explorer are registered trademarks of Parallels Software International, Inc. Virtuozzo, Plesk, HSPcomplete, and corresponding logos are trademarks of Parallels Holdings, Ltd. The Parallels logo is a trademark of Parallels Holdings, Ltd.

This product is based on a technology that is the subject matter of a number of patent pending applications. Virtuozzo is a patented virtualization technology protected by U.S. patents 7,099,948; 7,076,633; 6,961,868 and having patents pending in the U.S.

Plesk and HSPcomplete are patented hosting technologies protected by U.S. patents 7,099,948; 7,076,633 and having patents pending in the U.S.

Distribution of this work or derivative of this work in any form is prohibited unless prior written permission is obtained from the copyright holder.

Apple, Bonjour, Finder, Mac, Macintosh, and Mac OS are trademarks of Apple Inc.

Microsoft, Windows, Microsoft Windows, MS-DOS, Windows NT, Windows 95, Windows 98, Windows 2000, Windows XP, Windows 2003 Server, Windows Vista, Windows 2008, Microsoft SQL Server, Microsoft Desktop Engine (MSDE), and Microsoft Management Console are trademarks or registered trademarks of Microsoft Corporation.

Linux is a registered trademark of Linus Torvalds.

Red Hat is a registered trademark of Red Hat Software, Inc.

SUSE is a registered trademark of Novell, Inc.

Solaris is a registered trademark of Sun Microsystems, Inc.

X Window System is a registered trademark of X Consortium, Inc.

UNIX is a registered trademark of The Open Group.

IBM DB2 is a registered trademark of International Business Machines Corp.

SSH and Secure Shell are trademarks of SSH Communications Security, Inc.

MegaRAID is a registered trademark of American Megatrends, Inc.

PowerEdge is a trademark of Dell Computer Corporation.

eComStation is a trademark of Serenity Systems International.

FreeBSD is a registered trademark of the FreeBSD Foundation.

Intel, Pentium, Celeron, and Intel Core are trademarks or registered trademarks of Intel Corporation.

OS/2 Warp is a registered trademark of International Business Machines Corporation.

VMware is a registered trademark of VMware, Inc.

All other marks and names mentioned herein may be trademarks of their respective owners.

Contents

Introduction	5
About This Guide	5
Organization of This Guide	6
Documentation Conventions	6
Getting Help	7
Feedback	8
Parallels Virtual Automation Overview	9
Parallels Virtual Automation Components	10
Planning Your Parallels Virtual Automation Management System	12
Parallels Virtual Automation System Requirements	15
Parallels Server Bare Metal Computers	15
Hardware Requirements	16
Windows Computers	17
Software Requirements	18
Hardware Requirements	20
Linux Computers	21
Software Requirements	22
Hardware Requirements	23
Parallels Licensing Policy	23
Installing Parallels Virtual Automation Using Autoinstaller	24
Installing on Parallels Server Bare Metal Computers	24
Configuring Installation Settings	27
Installing on Windows-based Computers	28
Configuring Installation Settings	31
Installing on Linux-based Computers	31
Configuring Installation Settings	34
Installing PVA on Container via Autoinstaller	35
Installing Parallels Virtual Automation via Installation Archive	36
Installing PVA on Parallels Server Bare Metal Computers	36
Management Server and Control Center	36
PVA Agents for Parallels Server and Virtuozzo, Power Panel	40
Installing PVA on Windows-based Physical Servers	42
Management Server and Control Center	42
PVA Agent for Virtuozzo and Power Panel	45
Installing PVA on Linux-based Physical Servers	48
Management Server and Control Center	49
PVA Agent for Virtuozzo and Power Panel	52

Removing Parallels Virtual Automation Components	57
Removing From Parallels Server Bare Metal Computer	57
Removing From Windows-based Computer.....	58
Removing From Linux-based Computer	59
 Glossary	 60
 Index	 62

CHAPTER 1

Introduction

Parallels Virtual Automation is a flexible and easy-to-use administration tool designed for managing physical servers with Parallels Virtuozzo Containers and/or Parallels Server Bare Metal software. With Parallels Virtual Automation, you can create groups of physical servers and perform both collective and individual administration operations on these groups. Moreover, you can also manage the virtual environments residing on the registered physical servers: their productivity and resources, system tasks and processes, configuration, and much more. To work with the registered physical servers and their virtual environments, you will need a standard Web browser running on any platform.

You can read more about Parallels Virtual Automation and its functionality in **Parallels® Virtual Automation Administrator's Guide**.

In This Chapter

About This Guide.....	5
Getting Help.....	7
Feedback	8

About This Guide

This guide is aimed at a wide range of users who are new to Parallels Virtual Automation or just want to make sure they are doing everything right.

The present document is just as easy to use, as the product itself. However, we also provide complete information about the structure and peculiarities of the guide in the following topics.

Organization of This Guide

The structure of the present guide is quite transparent and consists of the following elements:

- The **Introduction** chapter (p. 5) provides basic information about the product and this guide.
- The **Parallels Virtual Automation Overview** chapter (p. 9) describes the basics of the Parallels Virtual Automation infrastructure concept and explains the PVA components structure.
- The **Parallels Virtual Automation System Requirements** chapter (p. 15) provides information about the system requirements your physical servers should meet to ensure successful installation.
- The **Installing Parallels Virtual Automation Using Autoinstaller** chapter (p. 24) provides detailed installation instructions for the autoinstaller.
- The **Installing Parallels Virtual Automation via Installation Archive** chapter (p. 36) provides detailed installation instructions for the installation archive.
- The **Removing Parallels Virtual Automation Components** chapter (p. 57) that instructs you how to remove the product or its components from a given computer.

Documentation Conventions

Before you start using this guide, it is important to understand the documentation conventions used in it.

The table below presents the existing formatting conventions:

Formatting Conventions	Type of information	Example
Special Bold	Items you must select, such as menu options, command buttons or items in a list.	Go to the Resources tab.
	Titles of chapters, sections and subsections.	Read the Basic Administration chapter.
<i>Italics</i>	Used to emphasize the importance of a point, to introduce a term or to designate a command line placeholder, which is to be replaced with a real name or value.	These are the so-called <i>EZ templates</i> . To destroy a Container, type <code>vzctl destroy <i>ctid</i></code> .
Monospace	The names of commands, files and directories.	Use <code>vzctl start</code> to start a Container.
Preformatted	On-screen computer output in your command line sessions; source code in XML, C++, or other programming languages.	<code>Saves parameters for Container 101</code>
Monospace Bold	What you type as contrasted with on-screen computer output.	<code># rpm -V virtuoizzo-release</code>
Key+Key	Key combinations for which the user should press and hold down one key and then press another.	Ctrl+P, Alt+F4

Besides the formatting conventions, you should also know about the document organization convention applied to Parallels documents: chapters in all guides are divided into sections, which, in turn, are subdivided into subsections. For example, **About This Guide** is a section, and **Documentation Conventions** is a subsection.

Getting Help

Parallels Virtual Automation offers several options for accessing necessary information:

Parallels Virtual Automation documentation

- **Parallels Virtual Automation Administrator's Guide.** This document contains extensive information about the product, its usage and troubleshooting. To access the PDF version of the document, go to the **Support** link in the left pane and then click the **Downloads** pane. You can download any document of the Parallels Virtual Automation documentation bundle from the Parallels website.
- **Parallels Virtual Automation Installation Guide.** This document contains extensive information on system requirements for physical computers and instructions how to install Parallels Virtual Automation components on them.
- **Getting Started With Parallels Virtual Automation.** This document contains the basic information how to install, launch and manage Parallels Virtual Automation.
- **Parallels Power Panel User's Guide.** This document contains extensive information about the Power Panel application.
- **Parallels Virtual Automation Upgrade Guide.** This document contains instructions on how to upgrade from Parallels Infrastructure Manager 4.0 to Parallels Virtual Automation 4.5.

Context-sensitive help

You can open a help page for the current screen by clicking the **Help** link in the right upper corner.

Parallels Web Site

Parallels web site <http://www.parallels.com>. Explore the Support web page that includes product help files and the FAQ section.

Parallels Knowledge Base

Parallels Knowledge Base <http://kb.parallels.com>. This online resource comprises valuable articles about using the Parallels Virtual Automation 4.5, Parallels Virtuozzo Containers and Parallels Server Bare Metal products.

Feedback

If you spot a typo in this guide, or if you have thought of a way to make this guide better, we would love to hear from you!

The ideal place for your comments and suggestions is the Parallels documentation feedback page (<http://www.parallels.com/en/support/usersdoc/>).

CHAPTER 2

Parallels Virtual Automation Overview

With Parallels Virtual Automation, you can easily deploy an effectively functioning virtual infrastructure that can help you significantly reduce your costs in terms of time and resources. While Parallels software virtualization products enable you to create complex formations of virtual environments, you may find it hard to manage these formations using different management tools. However, with Parallels Virtual Automation you can handle this challenging task with ease. Since Parallels Virtual Automation supports the whole set of the Parallels products, you can use it with any of its virtualization solutions, be it Parallels Virtuozzo Containers or Parallels Server Bare Metal products.

Of course, if you work with only one software virtualization product, you can just as well use the native management tool – Parallels Management Console (PMC) – designed to manage either Parallels Containers or Parallels virtual machines. However, if you build up your infrastructure with both software- and hardware-based virtualization, you need a more sophisticated tool for managing such infrastructure.

Why would you need to use both Parallels Containers and Parallels Server technologies? One of the primary reasons could be that you want to have virtual environments with guest OS different from the hosting physical server OS. With Parallels virtual machines, you can have a wide range of guest OSs installed on them.

At the same time, you can use Parallels Virtuozzo Containers software for creating Windows- and Linux-based virtual environments (depending on the physical server OS), as the resulting Containers are less resource consuming than virtual machines.

Parallels Virtual Automation enables you to manage complex groups of virtual environments, as well as particular Containers or virtual machines. Using Parallels Virtual Automation, you can form groups of physical servers and virtual environments, schedule physical server backups and other tasks; start, stop, and configure particular virtual environments, and much more. You can read more about Parallels Virtual Automation and its functionality in **Parallels® Virtual Automation Administrator's Guide**.

In This Chapter

Parallels Virtual Automation Components	10
Planning Your Parallels Virtual Automation Management System.....	12

Parallels Virtual Automation Components

Before you start installing Parallels Virtual Automation, you should learn about its components and their role in the management process. Parallels Virtual Automation consists of several components and an auxiliary tool. The main Parallels Virtual Automation components are:

Component	Where to install	Description
PVA Management Server	On any clean physical server without any software virtualization technology, or on a Container.* The physical server with PVA Management Server component installed is called <i>Master Server</i> .	This component ensures the communication between the slave physical servers and their virtual environments. PVA Control Center It is a part of the PVA Management Server component and is always installed together with it. Thus, you are able to interact with the remote physical servers and have means to observe your virtual infrastructure. It is the PVA front-end that you see in the browser window after logging in to Parallels Virtual Automation. When talking about the Parallels Virtual Automation interface, we are actually talking about the Control Center interface.
PVA Agent for Parallels Server	On a dedicated physical server that has Parallels Server Bare Metal software installed. Such server is also called a <i>Slave server</i> .	The component ensures the interaction between this physical server, the Master Server and your client computer. Without this component, a physical server cannot be registered in Management Server.
PVA Agent for Virtuozzo	On a dedicated physical server that has Parallels Virtuozzo Containers for Linux/Windows or Parallels Server Bare Metal software installed. Such server is also called a <i>Slave server</i> .	This component ensures the interaction between this physical server, the Master Server and your client physical computer. Without this component, a physical server cannot be registered in Management Server.
SNMP	On a dedicated physical server that has Parallels Virtuozzo Containers for Windows/Linux installed. Such server is also called a <i>Slave server</i> .	The PVA Agent for Virtuozzo on Windows physical servers includes the SNMP protocol distributive that is installed alongside with the Agent. On Linux physical servers, SNMP should be installed separately before the Agent component installation.

Parallels Power Panel	On a dedicated physical server together with PVA Agent component (PVA Agent for Virtuozzo or for Parallels Server).	<p>An auxiliary tool designed for managing a single virtual machine or a single Container. It can be installed only together with the PVA Agent component.</p> <p>Note: During the Parallels Power Panel installation, an auxiliary Service Container 1 is created. It ensures proper Parallels Power Panel functioning.</p> <p>SOAP protocol</p> <p>The Soap Agent part is installed alongside with the Power Panel component. Rejecting Power Panel installation, you will not be able to manage virtual environments via SOAP.</p>
-----------------------	---	---

* The PVA Management Server component cannot be installed directly on a Parallels Server Bare Metal physical server due to the virtualization software already installed on this server. The workaround solution is to create a Container on the PSBM physical server and to launch the PVA installation there. A Container is free from any virtualization technologies, so you can easily install PVA Management Server on it. To ensure a successful installation, the Container should be created on the basis of the `ve-slm.2048MB.conf-sample` template.


The PVA Management Server component cannot be as well installed on a dedicated Linux- or Windows-based physical server. But creating a Container on this physical server allows you to launch the PVA Management Server component installation inside it.

For the instructions on creating a Container, refer to the Parallels® Virtuozzo Containers for Linux user guide.

Planning Your Parallels Virtual Automation Management System

From the previous section, you know what components Parallels Virtual Automation consists of. Now you can pass on to creating your own management system.

Please pay attention to the following scheme. This is an example of a possible Parallels Virtual Automation management system. Of course, your management system may vary from the scheme below but nevertheless it will help you to understand the Parallels Virtual Automation basics more clearly.



So, let us analyze the Parallels Virtual Automation management system displayed on the scheme. It consists of:

Master Server

A Master Server is a physical server where all other subordinate physical servers are registered. On this physical server, PVA Management Server component should be installed.

Note: PVA Management Server component is always installed together with the PVA Control Center component.

What physical server can be used as a Master Server?

- A clean physical server that has no Parallels virtualization software installed. PVA Management Server component is installed directly on the physical server.
- A Linux-based physical server with Parallels Virtuozzo Containers software installed. As such physical server already has a software virtualization technology installed, you cannot install PVA Management Server component directly on it. First, you should create a Container by means of Parallels Virtuozzo Containers software and then install the PVA component inside the Container. In this case, the physical server can act as a Master Server and a Slave Server at the same time.
- A bare-metal physical server with Parallels Server Bare Metal software installed. This case is much alike the previous one. First, you should create a Container and then install the PVA Management Server component into it. The physical server also can act as a Master Server and a Slave Server at the same time.

For more information about the Parallels Virtual Automation components, please refer to **Parallels Virtual Automation Components** (p. 10). To know more about the Parallels Virtual Automation system requirements, please refer to **Parallels Virtual Automation System Requirements** (p. 15).

Slave Server

A Slave Server is a dedicated physical server that has one of the Parallels software virtual technologies installed. On this physical server, PVA Agent for Parallels Server and/or for Virtuozzo can be installed depending on the software virtualization technology the server already has. A bare metal computer with Parallels Server Bare Metal software installed allows you to install both PVA Agents, thus to have Containers and virtual machines on one and the same physical server.

A Slave Server should also have the Power Panel component installed. This ensures that a customer can manage the private virtual environment residing on the hosting physical server.

Note: PVA Agent component is installed by default together with the PVA Power Panel component.

What physical server can be used as a Slave Server?

- a Windows- or Linux-based physical server running Parallels Virtuozzo Containers;
- a bare metal physical server running Parallels Server Bare Metal.

Note: After you install all the necessary components on the physical servers, you should register your slave servers on Master Server.

Customer's Computer

Any computer can serve as a customer's computer provided that it has a stable network connection and a Web browser supported by Parallels Virtual Automation (p. 18). A customer's computer does not need any PVA components to be installed. The connection between the customer's computer and the PVA Slave Server's virtual environments is provided by the Parallels Power Panel installed on the Slave server.

Note: Parallels Power Panel allows working with a single private computer and does not provide access to the whole Slave Server or PVA management system.

CHAPTER 3

Parallels Virtual Automation System Requirements

After deciding on the structure of your Parallels Virtual Automation management system, please make sure that all the physical servers, which you are going to include in this system, meet the system and network requirements below.

In This Chapter

Parallels Server Bare Metal Computers	15
Windows Computers	17
Linux Computers.....	21
Parallels Licensing Policy	23

Parallels Server Bare Metal Computers

The modern Parallels software virtualization technologies allow you to effectively use bare metal computers, with Parallels Server Bare Metal installed, in the PVA management system.

A Parallels Server bare metal computer can take various roles in the management system:

- It can be used as a **Master Server** (p. 12) and should meet the system requirements for the PVA Management Server component.
- It can be used as a **Slave Server** (p. 12) and should meet the requirements for the PVA Agent for Parallels Server and for Virtuozzo components.

Hardware Requirements

If a Parallels Server bare metal computer serves as a Master Server (p. 10), there are no special requirements for it. However, below is the list of the basic hardware requirements you can use as a checklist:

- Intel Celeron, Pentium III, Pentium 4, Xeon, or AMD Athlon CPU;
- at least 1 GB of RAM;
- hard drive with at least 15 GB of free disk space;
- network card.

Bear in mind, that the PVA Management Server component, that converts a physical server into a Master Server, cannot be installed directly on a Parallels Server bare metal computer because it already has two Parallels virtualization technologies installed. First, you should create a Container and start the PVA component installation there. To ensure a successful installation, the Container should be created on the basis of the `ve-slm.2048MB.conf-sample` template. For the instructions on creating a Container, refer to the *Parallels® Virtuozzo Containers for Linux* user guide.

If a Parallels Server bare metal computer serves as a Slave Server (p. 10) where virtual environments will be stored and managed, then Parallels Virtual Automation will call for more complex hardware. The general considerations regarding the configuration of your physical servers could be as follows:

- CPUs. The more virtual environments you plan to run simultaneously, the more CPUs you need.
- Memory. The more memory you have, the more virtual environments you can run. The exact figure depends on the number and nature of applications you are planning to run in your virtual environments.
- Disk space. Each virtual environment occupies 40–150 MB of hard disk space for system files in addition to the user data inside the virtual environment (for example, web site content). You should consider it when planning disk partitioning and the number of virtual environments to run.
- Intel VT-x or AMD-V hardware virtualization technology support.

Note: The hardware requirements above serve as additional requirements and are true for the proper functioning of Parallels Virtual Automation only. The correct work of Containers and virtual machines is guaranteed by adhering to the system requirements of the Parallels Virtuozzo Containers and Parallels Server Bare Metal products.

For the detailed and more concrete information on the requirements for the Parallels Server Bare Metal computer, see *Parallels® Server Bare Metal Installation Guide*.

Windows Computers

This subsection focuses on the software and hardware requirements for the Windows-based physical servers where you are going to install the Parallels Virtual Automation components.

The modern Parallels software virtualization technologies allow you to effectively use Windows-based computers in the PVA management system.

A Windows-based computer can take various roles in the management system:

- It can be used as a **Master Server** (p. 12) and should meet the system requirements for the PVA Management Server component.
- It can be used as a **Slave Server** (p. 12) and should meet the requirements for the PVA Agent for Virtuozzo component.
- It can be used as a **Client computer** (p. 12) and doesn't need any PVA component to be installed, but still has some software requirements.

This subsection focuses on the software and hardware requirements for the Windows-based physical computers where you are going to install the Parallels Virtual Automation components.

Software Requirements

If a Windows-based computer serves as a Master Server (p. 10), it should be free from any software virtualization technology and can have an operating system with the following characteristics:

x86 full versions of Windows Server 2008 with or without Hyper-V:

- Windows Server 2008 with Service Pack 1 or Service Pack 2, Enterprise Edition (US English)
- Windows Server 2008 with Service Pack 1 or Service Pack 2, Standard Edition (US English)
- Windows Server 2008 with Service Pack 1 or Service Pack 2, Datacenter Edition (US English)
- Windows Server 2008 with Service Pack 2, Enterprise Edition (French, German, Japan, Italian, Korean, Spanish, Russian, and Simplified Chinese)
- Windows Server 2008 with Service Pack 2, Standard Edition (French, German, Japan, Italian, Korean, Spanish, Russian, and Simplified Chinese)
- Windows Server 2008 with Service Pack 2, Datacenter Edition (French, German, Japan, Italian, Korean, Spanish, Russian, and Simplified Chinese)

x86 full versions of Windows Server 2008 without Hyper-V:

- Windows Server 2008 with Service Pack 1, Datacenter Edition (German and Simplified Chinese)

x86 versions of Windows Server 2003:

- Standard or Enterprise Edition of Windows Server 2003 Service Pack 1 with or without R2: US English, German, French, Korean, Spanish, Traditional Chinese, Simplified Chinese, or Japanese
- Standard or Enterprise Edition of Windows Server 2003 Service Pack 2 with or without R2: US English, German, French, Italian, Korean, Russian, Spanish, Traditional Chinese, Simplified Chinese, or Japanese
- Standard or Enterprise Edition of Windows Server 2003 Service Pack 2 (Russian)
- Datacenter Edition of Windows Server 2003 Service Pack 1 with or without R2 (US English)
- Datacenter Edition of Windows Server 2003 Service Pack 2 with or without R2 (US English)

x64 full versions of Windows Server 2008 with or without Hyper-V:

- Windows Server 2008 with Service Pack 1 or Service Pack 2, Enterprise Edition (US English)
- Windows Server 2008 with Service Pack 1 or Service Pack 2, Standard Edition (US English)
- Windows Server 2008 with Service Pack 1 or Service Pack 2, Datacenter Edition (US English)

- Windows Server 2008 with Service Pack 2, Enterprise Edition (French, Japan, Italian, Korean, Spanish, Russian, and Simplified Chinese)
- Windows Server 2008 with Service Pack 2, Standard Edition (French, German, Japan, Italian, Korean, Spanish, Russian, and Simplified Chinese)
- Windows Server 2008 with Service Pack 2, Datacenter Edition (French, German, Japan, Italian, Korean, Spanish, Russian, and Simplified Chinese)

X64 full versions of Windows Server 2008 without Hyper-V:

- Windows Server 2008 with Service Pack 1, Datacenter Edition (German and Simplified Chinese)

x64 versions of Windows Server 2003:

- Standard or Enterprise Edition of Windows Server 2003 x64 Service Pack 1 with or without R2 (US English or Japanese)
- Standard or Enterprise Edition of Windows Server 2003 x64 Service Pack 2 with or without R2 (US English, French, German, Japanese, Italian, Korean, Simplified Chinese, Spanish, or Traditional Chinese)
- Standard or Enterprise Edition of Windows Server 2003 x64 Service Pack 2 (Russian)
- Datacenter Edition of Windows Server 2003 x64 Service Pack 1 with or without R2 (US English)
- Datacenter Edition of Windows Server 2003 x64 Service Pack 2 with or without R2 (US English)
- Datacenter Edition of Windows Server 2003 x64 with Service Pack 2 (Japanese)

A Windows-based computer may also serve as a Master Server even if it has a software virtualization technology installed - Parallels Virtuozzo Containers for Windows product. In this case, you should create a Container and start installing the corresponding PVA component there. For the instructions on creating a Container, refer to the Parallels® Virtuozzo Containers for Windows user guide.

If a Windows-based computer serves as a Slave Server (p. 10) where virtual environments will be stored and managed, then Parallels Virtual Automation will call for more complex requirements, as the creation and management of containers and virtual machines demand more complex software resources. So, in choosing an appropriate Windows-based computer, you should be guided by the Parallels Virtuozzo Containers system requirements. For the detailed and more concrete information on the requirements, see Parallels® Virtuozzo Containers for Linux and Parallels® Virtuozzo Containers for Windows user guides.

Note: The software requirements above serve as additional requirements and are true for the proper functioning of Parallels Virtual Automation only. The correct work of Containers is guaranteed by adhering to the system requirements of the Parallels Virtuozzo Containers product.

If a computer serves as a Client Server (p. 12), it should have one of the supported Web-browser clients:

- Internet Explorer 6.x and above for Windows;
- Mozilla Firefox 2.x and 3.x for all platforms;
- Safari 3.x for Mac;

Although other browsers will most likely work, only those listed above have been extensively tested for compatibility with Parallels Virtual Automation.

Hardware Requirements

If a Windows-based computer serves as a Master Server (p. 10), there are no special requirements for it. However, you can use the following list of the basic hardware requirements as a checklist:

- Intel Celeron, Pentium III, Pentium 4, Xeon, or AMD Athlon CPU;
- at least 1 GB of RAM;
- hard drive with at least 15 GB of free disk space;
- network card.

If a Windows-based computer serves as a Slave Server (p. 10) where virtual environments will be stored and managed, then Parallels Virtual Automation will call for more complex hardware. The general considerations regarding the configuration of your physical servers could be as follows:

- CPUs. The more virtual environments you plan to run simultaneously, the more CPUs you need.
- Memory. The more memory you have, the more virtual environments you can run. The exact figure depends on the number and nature of applications you are planning to run in your virtual environments.
- Disk space. Each virtual environment occupies 40–150 MB of hard disk space for system files in addition to the user data inside the virtual environment (for example, web site content). You should consider it when planning disk partitioning and the number of virtual environments to run.

Note: The hardware requirements above serve as additional requirements and are true for the proper functioning of Parallels Virtual Automation only. The correct work of Containers is guaranteed by adhering to the system requirements of the Parallels Virtuozzo Containers product.

For the detailed and more concrete information on the requirements for the computer, see [Parallels® Virtuozzo Containers for Linux](#) and [Parallels® Virtuozzo Containers for Windows](#) user guides.

Linux Computers

This subsection focuses on the software and hardware requirements for the Linux-based physical computers where you are going to install the Parallels Virtual Automation components.

The modern Parallels software virtualization technologies allow you to effectively use Linux-based computers in the PVA management system.

A Linux-based computer can take various roles in the management system:

- It can be used as a **Master Server** (p. 12) and should meet the system requirements for the PVA Management Server component.
- It can be used as a **Slave Server** (p. 12) and should meet the requirements for the PVA Agent for Virtuozzo component.
- It can be used as a **Client computer** (p. 12) and doesn't need any PVA component to be installed, but still has some software requirements.

This subsection focuses on the software and hardware requirements for the Linux-based physical computers where you are going to install the Parallels Virtual Automation components.

Software Requirements

If a Linux-based computer serves as a Master Server (p. 10), it should be a physical server without any software virtualization technology running x64 or i386 versions of SUSE 10, CentOS 4, CentOS 5, RHEL 4, RHEL 5.1, RHEL 5.2, RHEL 5.3.

A Linux-based computer can serve as a Master Server even if it has a software virtualization technology - Parallels Virtuozzo Containers for Linux software. In this case, you should create a Container and start the PVA installation there. The Container should be created on the basis of the `ve-slm.2048MB.conf-sample` template. For the instructions on creating a Container, refer to the [Parallels® Virtuozzo Containers for Linux user guide](#).

If a Linux-based computer serves as a Slave Server (p. 10) where virtual environments will be stored and managed, then Parallels Virtual Automation will call for more complex requirements, as the creation and management of containers and virtual machines demand more complex software resources. So, in choosing an appropriate Linux-based computer, you should be guided by the Parallels Virtuozzo Containers system requirements. For the detailed and more concrete information on the requirements, see [Parallels® Virtuozzo Containers for Linux](#) and [Parallels® Virtuozzo Containers for Windows](#) user guides.

If a computer serves as a Client Server (p. 12), it should have a supported Web-browser client:

- Internet Explorer 6.x and above for Windows;
- Mozilla Firefox 2.x and 3.x for all platforms;
- Safari 3.x for Mac;

Note: The software requirements above serve as additional requirements and are true for the proper functioning of Parallels Virtual Automation only. The correct work of Containers is guaranteed by adhering to the system requirements of the Parallels Virtuozzo Containers product.

Although other browsers will most likely work, only those listed above have been extensively tested for compatibility with Parallels Virtual Automation.

Hardware Requirements

If a Linux-based computer serves as a Master Server (p. 10), there are no special requirements for it. However, below is the list of the basic hardware requirements you can use as a checklist:

- Intel Celeron, Pentium III, Pentium 4, Xeon, or AMD Athlon CPU;
- at least 1 GB of RAM;
- hard drive with at least 15 GB of free disk space;
- network card.

If a Linux-based computer serves as a Slave Server (p. 10) where virtual environments will be stored and managed, then Parallels Virtual Automation will call for more complex hardware. The general considerations regarding the configuration of your physical servers could be as follows:

- CPUs. The more virtual environments you plan to run simultaneously, the more CPUs you need.
- Memory. The more memory you have, the more virtual environments you can run. The exact figure depends on the number and nature of applications you are planning to run in your virtual environments.
- Disk space. Each virtual environment occupies 40–150 MB of hard disk space for system files in addition to the user data inside the virtual environment (for example, web site content). You should consider it when planning disk partitioning and the number of virtual environments to run.

Note: The hardware requirements above serve as additional requirements and are true for the proper functioning of Parallels Virtual Automation only. The correct work of Containers is guaranteed by adhering to the system requirements of the Parallels Virtuozzo Containers product.

For the detailed and more concrete information on the requirements for the computer, see Parallels® Virtuozzo Containers for Linux and Parallels® Virtuozzo Containers for Windows user guides.

Parallels Licensing Policy

Parallels team provides flexible and easy-to-use solutions, which also applies to its licensing policy.

As such, Parallels Virtual Automation doesn't have a license of its own, and you can download and install it without accepting a license agreement. Instead, Parallels follows the *per-server licensing policy*, which means that you can use Parallels Virtual Automation only if you have a valid license for the Parallels virtualization software installed on your computer.

Installing Parallels Virtual Automation Using Autoinstaller

This section gives the detailed information on how to install Parallels Virtual Automation on Parallels Server bare metal, Windows- and Linux-based physical servers using the autoinstaller.

The autoinstaller scans the physical server and offers to download and to install those Parallels Virtual Automation components that can be installed on this server. Thus, the autoinstaller saves the downloading time and the disk space. The autoinstaller, through the internet, connects to the repository and downloads the necessary components.

Installing on Parallels Server Bare Metal Computers

You can install Parallels Virtual Automation on your Parallels Server Bare Metal physical server using the autoinstaller. This procedure consists of the following steps:

- 1 Download the necessary autoinstaller to the target Parallels Server bare metal physical server.
- 2 Go down to the directory, where the autoinstaller is stored.
- 3 Start the autoinstaller by executing the following command:

```
# ./autoinstaller_file_name
```

In the above command, `autoinstaller_file_name` stands for the name of the autoinstaller file.

- 4 In the **Welcome to pva-setup** window, click **Configure** to specify the Internet repository information and the local download directory to which you want to upload the files. For more information about the configuration settings, see **Configuring Installation Settings**:

```
Parallels Virtual Automation installer 4.5-145 -- (c) 1999-2009 Parallels
lqqqqqqqqqqqqqqqqqqqqqqqqqqqqquWelcome to pva-setuptqqqqqqqqqqqqqqqqqqqqqqqqqk
x                                                                                      x
x The pva-setup program will help you to install or upgrade                          x
x the Parallels Virtual Automation software on your computer                        x
x                                                                                      x
x                                                                                      x
x Current settings:                                                                  x
x                                                                                      x
x Full log is available at:                                                         x
x   /var/log/pva/setup/09.09.07_20.39.12_pva-setup.log                             x
x                                                                                      x
x Installation files will be taken from:                                           x
x   /vz/pva_agent/                                                                x
x                                                                                      x
x                                                                                      x
x                                                                                      x
x                                                                                      x
x                                                                                      x
x                                                                                      x
x tqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqu
x [ Quit ] [ Next ] [ Configure ] x
mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqj
ESC quit/cancel; ENTER default [< button >]; SPACE select/clear; TAB/BTAB change
```

Figure 1: Installing From TUI - Beginning Installation

After you have specified the necessary information, click **OK** and then **Next** to proceed with the installation.

- 5 In the **Choose installation type** window, choose the installation type. By default, you are offered to install PVA Agent for Virtuozzo, for Parallels Server, and the Power Panel component.

Note: To make a PSBM physical server function as a Master Server, you need to create a Container on this server and launch the PVA installation there. Refer to the **Installing PVA on Container via Autoinstaller** section (p. 35).

```

Parallels Virtual Automation installer 4.5-145 -- (c) 1999-2009 Parallels
lqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqChoose installation typetqqqqqqqqqqqqqqqqqqqqqqqk
x                                                                 x
x The Parallels Virtual Automation software is not installed on this      x
x computer. Please choose installation type.                               x
x                                                                 x
x lqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqInstallation typesqqqqqqqqqqqqqqqqqqqqqqqqqk x
x x(*)Default installation (Virtuozzo Agent & Power Panel, Parallels Age x x
x x ( ) Custom installation                                              x x
x x                                                                    x x
x x                                                                    x x
x x                                                                    x x
x x                                                                    x x
x x                                                                    ax x
x x                                                                    ax x
x x                                                                    ax x
x x                                                                    ax x
x x                                                                    ax x
x x                                                                    ax x
x x                                                                    ax x
x mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqj x
tqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqq
x [ Back ] [ Next ] x
mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqj
ESC quit/cancel; ENTER default [< button >]; SPACE select/clear; TAB/BTAB change

```


Configuring Installation Settings

In the **Configure** window, you can set up the following parameters:

[illegible]

- **Repository URL:** the URL of the server storing the repository with the product installation files.
- **Repository login:** the user name to log in to the repository.
- **Repository password:** the password of the user specified in the **Repository login** field.
- **Proxy host[:port]:** (for those who use proxy server) the hostname or IP address of the proxy server to be used to connect to the repository.
- **Proxy login:** the user name used by the proxy server for your authentication.
- **Proxy password:** the password of the user specified in the **Proxy login** field and used for your authentication by the proxy server.
- **Download directory:** the directory on your server where the installation files will be downloaded to.

To edit the settings, click the text field and type/edit the text.

Installing on Windows-based Computers

You can install Parallels Virtual Automation on your Windows-based physical server using the autoinstaller. This procedure consists of the following steps:

- 1 Download the necessary autoinstaller to the target Windows-based physical server.
- 2 Start the autoinstaller by double-clicking it.
- 3 In the **Welcome** window, click **Configure Settings** to specify the Internet repository information and the local download directory to which you want to upload the Parallels Virtual Automation installation files. For more information about the configuration settings, see *Configuring Parallels Virtual Automation Installation* (p. 31).
- 4 When the necessary information is specified, click **Next** to proceed with the installation.
- 5 In the **Choose Setup Type** window, choose the installation type. The component for the default installation may differ. This depends on whether the physical server is clean or already has any software virtualization technology installed on it.
 - If the physical server is clean (i.e. has no virtualization technology installed), you will be offered to install the PVA Management Server component by default. Click **Next** to start the installation. If you want to change the destination folder for the Management Server component, choose **Custom installation** and click **Next**.




Figure 2: Installing PVA Management Server on Windows - Selecting Default Installation

- If the physical server has Parallels Virtuozzo Containers installed, you will be offered to install the PVA Agent for Virtuozzo component by default.




Figure 3: Installing From GUI - Selecting Custom Installation

Click **Next** to start the installation. Keep in mind that, by default, the wizard will install both the PVA Agent for Virtuozzo and PVA Power Panel components. If you want to deselect PVA Power Panel or select SNMP for installation, select **Custom installation** and click **Next**. Pass on to the next step.

- 6 After you have selected Custom installation, you will see the Choose components to install window displayed. Select the components to be installed.





Figure 4: Installing From GUI - Choosing Components

You can manually select where the program files will be placed by typing the path in the Choose destination folder field.

- 7 Click Next to start the installation.

Configuring Installation Settings

In the PVA setup window, you should set up the following parameters:



The screenshot shows the 'PVA Setup' window with the title 'PVA setup' and subtitle 'Configuring PVA installation'. It contains four input fields: 'Repository URL' with the value 'http://download.pa.parallels.com/pva/4.5/repo/mn', 'Repository login' (empty), 'Repository password' (empty), and 'Download directory' with the value 'C:\Documents and Settings\Administrator'. At the bottom are buttons for '< Back', 'Next >', and 'OK'.

- **Repository URL:** the URL of the server storing the repository with the product installation files.
- **Repository login:** the user name to log in to the repository.
- **Repository password:** the password of the user specified in the Repository login field.
- **Download directory:** the directory on your server where the installation files will be downloaded on.

To edit the settings, click the text field, type/edit the text, and click OK.

Installing on Linux-based Computers

You can install Parallels Virtual Automation on your Linux-based physical server using the autoinstaller. This procedure consists of the following steps:

- 1 Download the necessary autoinstaller to the target Linux-based physical server.
- 2 Go down to the directory, where the autoinstaller is stored.
- 3 Start the autoinstaller by executing the following command:

```
# ./autoinstaller_file_name
```

In the above command, `autoinstaller_file_name` stands for the name of the autoinstaller file.

- **Repository URL:** the URL of the server storing the repository with the product installation files.
- **Repository login:** the user name to log in to the repository.
- **Repository password:** the password of the user specified in the **Repository login** field.
- **Proxy host[:port]:** (for those who use proxy server) the hostname or IP address of the proxy server to be used to connect to the repository.
- **Proxy login:** the user name used by the proxy server for your authentication.
- **Proxy password:** the password of the user specified in the **Proxy login** field and used for your authentication by the proxy server.
- **Download directory:** the directory on your server where the installation files will be downloaded on.

To edit the settings, click the text field and type/edit the text.

Installing PVA on Container via Autoinstaller

You will need to install PVA on a Container in the following situation: you have a physical server with a software virtualization technology installed (a Parallels Server Bare Metal physical server or Windows-/Linux-based physical server with Parallels Virtuozzo Containers software installed). It means that the physical server already has a software virtualization technology, and you cannot convert this server into a Master Server. But you can create a Container, that has no software virtualization technology, and use this Container to install the **Management Server** component (p. 10) of PVA, thus you convert the whole physical server into a Master Server.

Creating a Container

To ensure a successful installation of the PVA components in the Container, you should create a Container with a particular configuration. On Parallels Server bare metal and Linux-based physical servers, use the `ve-slm.2048MB.conf-sample`, on the basis of which you should create the Container. A Container on a Windows-based physical server can be created on the basis of any template.

For the instruction on creating a Container refer to the **Parallels® Virtuozzo Containers for Linux** and **Parallels® Virtuozzo Containers for Windows** user guides.

Running PVA Autoinstaller on a Container

After you have created a Container, you can start the PVA Autoinstaller inside. The Autoinstaller behavior principles are absolutely the same as if you were running it on a real physical server with Linux- or Windows-based operating system. So, for the detailed instructions, you can refer to the **Installing on Linux-Based Computers** section (p. 31). or to the **Installing on Windows-based Computers** section (p. 28).

Installing Parallels Virtual Automation via Installation Archive

This subsection contains a detailed description on how to install Parallels Virtual Automation, using the installation archives, on various platforms.

Installing PVA on Parallels Server Bare Metal Computers

Different PVA components can be installed from different archives:

If you want to have a Parallels Server Bare Metal computer serve as a **Master Server** (p. 12), you should use one type of archives that allow you to install the Management Server and Control Center.

If you want to have a Parallels Server Bare Metal computer serve a **Slave Server** (p. 12), you should use another type of archives that allow you to install PVA Agent for Parallels Server.

Management Server and Control Center

Management Server is a PVA component that converts a physical server into a Master Server and that can be installed on a physical server without any software virtualization technology primarily installed.

Bear in mind, that this component cannot be installed directly on a bare metal computer because it already has Parallels Server Bare Metal software installed. First, you should create a Container with the help of Parallels Virtuozzo Containers and start the PVA component installation there. For the instructions on creating a Container, refer to the *Parallels® Virtuozzo Containers for Linux* user guide.

You can conduct the installation procedure using either terminal user interface (TUI) or command-line interface (CLI). These two ways are described in detail in the following subsections.

- 5 In the Choose installation type window, you will be offered to install the PVA Management Server component by default.

```

Parallels Virtual Automation installer 4.5-144 -- (c) 1999-2008 Parallels
lqqqqqqqqqqqqqqqqqqqqqqqqqqqqChoose installation typetqqqqqqqqqqqqqqqqqqqqqqqk
x
x The Parallels Virtual Automation software is not installed on this      x
x computer. Please choose installation type.                               x
x                                                                           x
x lqqqqqqqqqqqqqqqqqqqqqqqqqqqqInstallation typesqqqqqqqqqqqqqqqqqqqqqqqqk x
x x(*)Default installation (Management Server)                            x x
x x( )Custom installation                                                  x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        ax x
x x                                                                        ax x
x x                                                                        ax x
x x                                                                        ax x
x x                                                                        ax x
x x                                                                        ax x
x mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqj x
tqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqu
x [ Back ] [ Next ] x
mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqj
ESC quit/cancel; ENTER default [< button >]; SPACE select/clear; TAB/BTAB change

```

Figure 9: Installing PVA Management Server on Linux - Selecting Default Installation

Click Next to start the installation.

Unattended Installation

If you prefer to use the command-line interface to install Parallels Virtual Automation on your bare metal-based physical server, you have to specify a number of PVA components (p. 10) after the `--install` command of the `pva-setup` utility and the program will use them to install the product.

Note: The Management Server component cannot be installed directly on the Parallels Server Bare Metal computer. You should primarily create a Parallels Virtuozzo Container. See Bare Metal system requirements (p. 16).

Besides a number of components used with the `--install` command, the `pva-setup` utility also provides you with a set of its own options that you can specify to configure, for example, the online installation. The options of the `pva-setup` utility are described in the following table:

Note: To be able to install Parallels Virtual Automation, you must be logged in with the `root` privileges.

Option	Description
<code>-h, --help</code>	Shows the installer help.
<code>-v, --verbose</code>	Prints the verbose output.

<code>-r, --repository <repository_address></code>	<p>This option is used when the installation files are stored in an online repository.</p> <p>Specify the Internet address of the remote repository to enable the installer download the required files to your computer.</p> <p>If you already have the installation files on the given computer, set the <code><repository_address></code> value to <code>local</code>.</p>				
<code>-d, --downloadaddr <dir_path></code>	Specifies the local directory, to which the installation files will be downloaded during the installation.				
<code>-l, --logdir <dir_path></code>	Specifies the path to the local folder where the installation logs will be stored.				
<code>--os_distributive_path <path></code>	Specifies the path to the distribution set of your operating system.				
<code>--install [-c <list_of_components>] [-u <versions>]</code>	<p>Installs/upgrades the specified Parallels Virtual Automation components.</p> <table border="1"> <tr> <td> <code>-c, --components <list_of_components></code> </td><td> <p>Specifies the list of components to install. Component names should be separated by commas:</p> <p><code>-c 'PVA Control Center, PVA Management Server'</code></p> </td></tr> <tr> <td> <code>-u, --update <version></code> </td><td> <p>Specifies the version to which you want to upgrade.</p> <p>Note: The update mechanism is still in development.</p> </td></tr> </table>	<code>-c, --components <list_of_components></code>	<p>Specifies the list of components to install. Component names should be separated by commas:</p> <p><code>-c 'PVA Control Center, PVA Management Server'</code></p>	<code>-u, --update <version></code>	<p>Specifies the version to which you want to upgrade.</p> <p>Note: The update mechanism is still in development.</p>
<code>-c, --components <list_of_components></code>	<p>Specifies the list of components to install. Component names should be separated by commas:</p> <p><code>-c 'PVA Control Center, PVA Management Server'</code></p>				
<code>-u, --update <version></code>	<p>Specifies the version to which you want to upgrade.</p> <p>Note: The update mechanism is still in development.</p>				
<code>--list</code>	Prints a list of updates and components you can install on the given computer.				
<code>--uninstall</code>	Removes Parallels Virtual Automation and all its components.				

The following example demonstrates how to install Parallels Virtual Automation on your bare metal physical server via the command-line interface:

- 1 Log in to the server with the `root` privileges.
- 2 Locate the Parallels Virtual Automation distribution and go down to the directory, where the `pva-setup` binary is stored.
- 3 Specify the necessary options and components after the `--install` command of the `pva-setup` utility:
 - To install only the PVA Management Server component, execute the following command:

```
# ./pva-setup --install -c "PVA Management Server"
```

The specified component will be installed on the server.

PVA Agents for Parallels Server and Virtuozzo, Power Panel

PVA Agent for Parallels Server or Virtuozzo is a PVA component that converts a physical server into a Slave Server and that can be installed on a physical server with Parallels Virtuozzo Containers or Parallels Server Bare Metal software.

You can conduct the installation procedure using either terminal user interface (TUI) or command-line interface (CLI). These two ways are described in detail in the following subsections.

Using TUI

If you are more accustomed to using a GUI installer, than to typing commands in Terminal, use the TUI wizard that will lead you through the installation process.

To install the PVA Agent for Parallels Server component from TUI, perform the following actions:

- 1 Log in to the target bare metal physical computer running Parallels Server Bare Metal as a user with the `root` privileges.
- 2 Locate the Parallels Virtual Automation distribution and go down to the directory, where the `pva-setup` binary is stored.
- 3 Execute the following command:

```
# ./pva-setup
```

- 4** In the **Welcome to pva-setup** window, click **Next** to proceed with the installation

```
Parallels Virtual Automation installer 4.5-145 -- (c) 1999-2009 Parallels
lqqqqqqqqqqqqqqqqqqqqqqqqqqqqquWelcome to pva-setuptqqqqqqqqqqqqqqqqqqqqqqqqqk
x                                                                 x
x The pva-setup program will help you to install or upgrade      x
x the Parallels Virtual Automation software on your computer     x
x                                                                 x
x                                                                 x
x Current settings:                                              x
x                                                                 x
x Full log is available at:                                       x
x /var/log/pva/setup/09.09.07_20.39.12_pva-setup.log              x
x                                                                 x
x Installation files will be taken from:                          x
x /vz/pva_agent/                                                  x
x                                                                 x
x                                                                 x
x                                                                 x
x                                                                 x
x                                                                 x
x tqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqu
x [ Quit ] [ Next ] [ Configure ] x
x mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqj
ESC quit/cancel; ENTER default [< button >]; SPACE select/clear; TAB/BTAB change
```

- 5 In the **Choose installation type** window, you will be offered to install the PVA Agents for Parallels Server and Virtuozzo components by default. Click **Next** to start the installation.

Keep in mind that, by default, the wizard will install both the PVA Agents and PVA Power Panel components.

If you want to deselect PVA Power Panel, select **Custom installation** and click **Next**.

- 6 In the Choose components to Install window, deselect the PVA Power Panel. Click Next to start the installation.

```

Parallels Virtual Automation installer 4.5-145 -- (c) 1999-2009 Parallels
lqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqChoose components to installtqqqqqqqqqqqqqqqqqqqqk
x                                     x
x lqqqqqqqqqqqqqqqqqqqqqqqqqqqqParallels Virtual Automationqqqqqqqqqqqqqqqqqqqqk x
x x[x] PVA Power Panel                                     x x
x x[x] PVA Agent for Parallels Server                       x x
x x[x] PVA Agent for Virtuozzo                             x x
x x[ ] SNMP                                                 x x
x x                                                         x x
x x                                                         x x
x x                                                         x x
x x                                                         x x
x x                                                         x x
x x                                                         x x
x x                                                         x x
x x                                                         x x
x x                                                         x x
x x                                                         x x
x x                                                         x x
x x                                                         x x
x mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqq] x
tqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqq]
x                                     [ Back ] [ Next ] x
mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqq]
ESC quit/cancel; ENTER default [< button >]; SPACE select/clear; TAB/BTAB change

```

Unattended Installation

In some cases, installing Parallels Virtual Automation components from command-line may be a faster solution compared against the TUI wizard. You only need to specify a number of parameters after the `install` command, and the program will use them to install the product.

The command you should run to install PVA Agent for Parallels Server on a bare metal physical computer running Parallels Server Bare Metal is the following:

```
# ./pva-setup --install -c "PVA Agent for Parallels Server"
```

If you want to install the PVA Agent for Parallels Server and PVA Power Panel components, execute the following command:

```
# ./pva-setup --install -c "PVA Agent for Parallels Server, PVA Power Panel"
```

Besides a number of parameters used with the `--install` command, the `pva-setup` utility also provides you with a set of its own parameters that you can use to configure on-line installation, for example. The table below lists all available parameters and their usage description.

Note: To be able to install Parallels Virtual Automation, you must be logged in as a user with root privileges.

Parameter	Description
-h, --help	Show the installer help.
-v, --verbose	Print verbose output.

<code>-r, --repository <repository_address></code>	Used when the installation files are stored in an on-line repository. Specify the Internet address of the remote repository to enable the installer download the required files to your computer. If you already have the installation files on the given computer, set the <code><repository_address></code> value to <i>local</i> .
<code>-d, --downloadaddr <dir_path></code>	Specifies the local directory, to which the installation files will be downloaded during installation.
<code>-l, --logdir <dir_path></code>	Specifies the path to the local folder where the installation logs will be stored.
<code>--os_distributive_path <path></code>	Specifies the path to the distribution set of your operating system.
<code>--install [-c <list_of_components>] [-u <versions>]</code>	<div>Install/upgrade the specified Parallels Virtual Automation components.</div> <div> <div> <code>-c, --components <list_of_components></code> <div>Specifies the list of components to install. Component names should be separated by comma: <code>-c 'PVA Agent for Parallels Server, PVA Agent for Virtuozzo, PVA Power Panel'</code> </div> </div> <div> <code>-u, --update <version></code> <div>Specifies the version to which you want to upgrade. Note: The update mechanism is still in development. </div> </div> </div>
<code>--list</code>	Prints a list of updates and components you can install on the given computer.
<code>--uninstall</code>	Removes Parallels Virtual Automation and all its components.

Installing PVA on Windows-based Physical Servers

This section gives detailed information on how to install Parallels Virtual Automation on Windows-based physical servers.

Management Server and Control Center

Management Server is a PVA component that converts a physical server into a Master Server and that can be installed on a physical server without any software virtualization technology primarily installed.

You can conduct the installation procedure using either graphical user interface (GUI) or command-line interface (CLI). These two ways are described in detail in the following subsections.

Using GUI

If you prefer to use a GUI installer, than to type commands in command line, use the GUI wizard that will lead you through the installation process.

Note: The Windows-based computer can be made a Master Server even if it already has Parallels Virtuozzo Containers installed on it. To do that, you should create a Parallels Virtuozzo Container (p. 18) and launch the PVA installation process there. The Container itself has no virtualization technology installed inside, and thus, Management Server component will be offered for the installation by default. The procedure of installation is the same as if you were installing PVA on a physical Windows-based computer.

To install the Management Server component on your Windows-based physical server, perform the following actions:

- 1 Log in to the physical server as Administrator.
- 2 Locate the Parallels Virtual Automation distribution set and double-click the `pva-setup-gui.exe` file to launch the Parallels Virtual Automation installation wizard.
- 3 In the Welcome window, click **Next** to proceed with the installation.
- 4 In the **Choose Setup Type** window, choose the installation type. By default, you are offered to install PVA Management Server, because you do not have Parallels Virtuozzo Containers installed on the physical server you are currently logged into.




Figure 10: Installing PVA Management Server on Windows - Selecting Default Installation

If you need to select where the program files will be placed, click **Custom installation** and change the path in the **Choose Destination folder** field.

5 Click **Next** to start the installation.

Unattended installation

If you prefer to use the command-line interface to install Parallels Virtual Automation on your bare metal-based physical server, you have to specify a number of PVA components (p. 10) after the `--install` command of the `pva-setup` utility and the program will use them to install the product.

Note: The Windows-based computer can be made a Master Server even if it already has Parallels Virtuozzo Containers installed on it. To do that, you should create a Parallels Virtuozzo Container (p. 18) and launch the PVA installation process there. The Container itself has no software virtualization technology installed inside, and thus, Management Server component will be offered for the installation by default. The procedure of installation is the same as if you were installing PVA on a physical Windows-based computer.

Besides a number of components used with the `--install` command, the `pva-setup.exe` utility also provides you with a set of its own options that you can specify to configure, for example, the on-line installation. The options of the `pva-setup.exe` utility are described in the following table:

Option	Description				
<code>-h, --help</code>	Shows the installer help.				
<code>-v, --verbose</code>	Prints the verbose output.				
<code>-r, --repository <repository_address></code>	<p>This option is used when the installation files are stored in an on-line repository.</p> <p>Specify the Internet address of the remote repository to enable the installer download the required files to your computer.</p> <p>If you already have the installation files on the given computer, set the <code><repository_address></code> value to <code>local</code>.</p>				
<code>-d, --downloadaddr <dir_path></code>	Specifies the local directory, to which the installation files will be downloaded during the installation.				
<code>-l, --logdir <dir_path></code>	Specifies the path to the local folder where the installation logs will be stored.				
<code>--os_distributive_path <path></code>	Specifies the path to the distribution set of your operating system.				
<code>--install [-c <list_of_components>] [-u <versions>]</code>	<p>Installs/upgrades the specified Parallels Virtual Automation components.</p> <table border="1"> <tr> <td> <code>-c, --components <list_of_components></code> </td><td> <p>Specifies the list of components to install. Component names should be separated by commas:</p> <p><code>-c 'PVA Control Center, PVA Management Server'</code></p> </td></tr> <tr> <td> <code>-u, --update <version></code> </td><td> <p>Specifies the version to which you want to upgrade.</p> <p>Note: The update mechanism is still in development.</p> </td></tr> </table>	<code>-c, --components <list_of_components></code>	<p>Specifies the list of components to install. Component names should be separated by commas:</p> <p><code>-c 'PVA Control Center, PVA Management Server'</code></p>	<code>-u, --update <version></code>	<p>Specifies the version to which you want to upgrade.</p> <p>Note: The update mechanism is still in development.</p>
<code>-c, --components <list_of_components></code>	<p>Specifies the list of components to install. Component names should be separated by commas:</p> <p><code>-c 'PVA Control Center, PVA Management Server'</code></p>				
<code>-u, --update <version></code>	<p>Specifies the version to which you want to upgrade.</p> <p>Note: The update mechanism is still in development.</p>				

<code>--list</code>	Prints a list of updates and components you can install on the given computer.
<code>--uninstall</code>	Removes Parallels Virtual Automation and all its components.

The following example demonstrates how to install Parallels Virtual Automation on your Windows-based physical server via the command-line interface:

- 1 Log in to the server with the Administrator privileges.
- 2 Open the command-line interface and go to the directory, where `pva-setup.exe` is stored.
- 3 Specify the necessary options and components after the `--install` command of the `pva-setup.exe` utility:
 - To install only the PVA Management Server component, execute the following command:

```
>pva-setup.exe --install -c "PVA Management Server"
```

The specified component will be installed on the server.

Note: To be able to install Parallels Virtual Automation, you must be logged in with the Administrator privileges.

PVA Agent for Virtuozzo and Power Panel

PVA Agent for Virtuozzo is a PVA component that converts a physical server into a Slave Server and that can be installed on a physical server with Parallels Virtuozzo Containers software installed.

You can conduct the installation procedure using either graphical user interface (GUI) or command-line interface (CLI). These two ways are described in detail in the following subsections.

Using GUI

If you prefer to follow a step-by-step procedure rather than use command-line options, use the GUI wizard to install PVA Agent for Virtuozzo and Power Panel:

- 1 Log in to the target Windows-based physical server as Administrator.
- 2 Locate the Parallels Virtual Automation distribution set and open `pva-setup-gui.exe`.
The Parallels Virtual Automation install wizard launches.

- 3 In the Welcome window, click **Next** to proceed with the installation.
- 4 In the **Choose Setup Type** window, you will be offered to install PVA Agent for Virtuozzo by default. Click **Next** to start the installation.




Figure 11: Installing From GUI - Selecting Custom Installation

Keep in mind that, by default, the wizard will install both the PVA Agent for Virtuozzo and PVA Power Panel components.

If you want to deselect PVA Power Panel, select **Custom installation** and click **Next**.

- 5 In the Custom Setup window, deselect the Power Panel component and click **Next** to start the installation.




Figure 12: Installing From GUI - Choosing Components

Unattended installation

In some cases, installing PVA components from command-line may be a faster solution compared against the GUI wizard. You only need to specify a number of parameters after the `install` command, and the program will use them to install the product.

The command you should run to install PVA Agent for Virtuozzo on a Windows-based computer running Parallels Virtuozzo Containers is the following:

```
# ./pva-setup --install -c "PVA Agent for Virtuozzo"
```

If you want to install the PVA Agent for Virtuozzo and PVA Power Panel components, execute the following command:

```
# ./pva-setup --install -c "PVA Agent for Virtuozzo, PVA Power Panel"
```

Besides a number of parameters used with the `install` command, the `pva-setup` utility also provides you with a set of its own parameters that you can use to configure on-line installation, for example. The table below lists all available parameters and their usage description.

Note. To be able to install Parallels Virtual Automation, you must be logged in as Administrator.

Parameter	Description
-h, --help	Show the installer help.

-v, --verbose	Print verbose output.
-r, --repository <repository_address>	Used when the installation files are stored in an on-line repository. Specify the Internet address of the remote repository to enable the installer download the required files to your computer. If you already have the installation files on the given computer, set the <repository_address> value to <i>local</i> .
-d, --downloadaddir <dir_path>	Specifies the local directory, to which the installation files will be downloaded during installation.
-l, --logdir <dir_path>	Specifies the path to the local folder where the installation logs will be stored.
--os_distributive_path <path>	Specifies the path to the distribution set of your operating system.
--install [-c <list_of_components>] [-u <versions>]	Install/upgrade the specified Parallels Virtual Automation components. -c, --components <list_of_components> Specifies the list of components to install. Component names should be separated by comma: -c 'PVA Agent for Virtuozzo, PVA Power Panel' -u, --update <version> Specifies the version to which you want to upgrade. Note. The update mechanism is still in development.
--list	Prints a list of updates and components you can install on the given computer.
--uninstall	Removes Parallels Virtual Automation and all its components.

Installing PVA on Linux-based Physical Servers

This section gives the detailed information on how to install Parallels Virtual Automation on Linux-based physical servers.

Management Server and Control Center

Management Server is a PVA component that converts a physical server into a Master Server and that can be installed on a physical server without any software virtualization technology primarily installed.

You can conduct the installation procedure using either terminal user interface (TUI) or command-line interface (CLI). These two ways are described in detail in the following subsections.

<code>-l, --logdir <dir_path></code>	Specifies the path to the local folder where the installation logs will be stored.
<code>--os_distributive_path <path></code>	Specifies the path to the distribution set of your operating system.
<code>--install [-c <list_of_components>] [-u <versions>]</code>	<div> <div>Installs/upgrades the specified Parallels Virtual Automation components.</div> <div> <div> <code>-c, --components <list_of_components></code> </div> <div>Specifies the list of components to install. Component names should be separated by commas: <code>-c 'PVA Control Center, PVA Management Server'</code> </div> </div> <div> <div> <code>-u, --update <version></code> </div> <div>Specifies the version to which you want to upgrade. Note: The update mechanism is still in development. </div> </div> </div>
<code>--list</code>	Prints a list of updates and components you can install on the given computer.
<code>--uninstall</code>	Removes Parallels Virtual Automation and all its components.

The following example demonstrates how to install Parallels Virtual Automation on your Linux-based physical server via the command-line interface:

- 1 Log in to the server with the `root` privileges.
- 2 Locate the Parallels Virtual Automation distribution and go down to the directory, where the `pva-setup` binary is stored.
- 3 Specify the necessary options and components after the `--install` command of the `pva-setup` utility:
 - If you want to install only the PVA Management Server component, execute the following command:

```
# ./pva-setup --install -c "PVA Management Server"
```

The specified component will be installed on the server.

Note: To be able to install Parallels Virtual Automation, you must be logged in with the `root` privileges.

PVA Agent for Virtuozzo and Power Panel

PVA Agent for Virtuozzo is a PVA component that converts a physical server into a Slave Server and that can be installed on a physical server with Parallels Virtuozzo Containers software installed.

You can conduct the installation procedure using either terminal user interface (TUI) or command-line interface (CLI). These two ways are described in detail in the following subsections.


```

Parallels Virtual Automation installer 4.5-144 -- (c) 1999-2008 Parallels
lqqqqqqqqqqqqqqqqqqqqqqqqqqqqChoose installation typetqqqqqqqqqqqqqqqqqqqqqqqk
x
x The Parallels Virtual Automation software is not installed on this      x
x computer. Please choose installation type.                               x
x
x WARNING! Parallels Virtual Automation                                  x
x will upgrade current installation of Parallels Infrastructure Manager    x
x
x lqqqqqqqqqqqqqqqqqqqqqqqqqqqqInstallation typesqqqqqqqqqqqqqqqqqqqqqqqqk x
x x(*)Default installation (Virtuozzo Agent & Power Panel)                x x
x x( )Custom installation                                                  x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        ax x
x x                                                                        ax x
x x                                                                        ax x
x x                                                                        ax x
x mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqq] x
tqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqu
x [ Back ] [ Next ] x
mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqq]
ESC quit/cancel; ENTER default [< button >]; SPACE select/clear; TAB/BTAB change

```

Figure 16: Installing From TUI - Choosing Installation Type

Keep in mind that, by default, the wizard will install both the PVA Agent for Virtuozzo and PVA Power Panel components.

If you want to deselect PVA Power Panel, select Custom installation and click Next.

- 6 In the Choose components to install window, deselect the Power Panel component and click Next to start the installation.

```

Parallels Virtual Automation installer 4.5-144 -- (c) 1999-2008 Parallels
lqqqqqqqqqqqqqqqqqqqqqqqqqqqqChoose components to installtqqqqqqqqqqqqqqqqqqqqqqqk
x
x lqqqqqqqqqqqqqqqqqqqqqqqqqqqqParallels Virtual Automationqqqqqqqqqqqqqqqqqqqqk x
x x[x] PVA Power Panel                                                    x x
x x[ ] PVA Agent for Parallels Server                                    x x
x x[x] PVA Agent for Virtuozzo                                           x x
x x[ ] SNMP                                                                x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x x                                                                        x x
x mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqq] x
tqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqu
x [ Back ] [ Next ] x
mqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqqq]
ESC quit/cancel; ENTER default [< button >]; SPACE select/clear; TAB/BTAB change

```

Figure 17: Installing From TUI - Selecting Components

Unattended installation

In some cases, installing Parallels Virtual Automation components from command-line may be a faster solution compared against the GUI wizard. You only need to specify a number of parameters after the `install` command, and the program will use them to install the product.

The command you should run to install PVA Agent for Virtuozzo on a Linux-based computer is the following:

```
# ./pva-setup --install -c "PVA Agent for Virtuozzo"
```

If you want to install the PVA Agent for Parallels Server and PVA Power Panel components, execute the following command:

```
# ./pva-setup --install -c "PVA Agent for Virtuozzo, PVA Power Panel"
```

Besides a number of parameters used with the `--install` command, the `pva-setup` utility also provides you with a set of its own parameters that you can use to configure online installation, for example. The table below lists all available parameters and their usage description.

Note: To be able to install Parallels Virtual Automation, you must be logged in as a user with root privileges.

Parameter	Description
<code>-h, --help</code>	Show the installer help.
<code>-v, --verbose</code>	Print verbose output.
<code>-r, --repository <repository_address></code>	Used when the installation files are stored in an on-line repository. Specify the Internet address of the remote repository to enable the installer download the required files to your computer. If you already have the installation files on the given computer, set the <code><repository_address></code> value to <code>local</code> .
<code>-d, --downloadaddr <dir_path></code>	Specifies the local directory, to which the installation files will be downloaded during installation.
<code>-l, --logdir <dir_path></code>	Specifies the path to the local folder where the installation logs will be stored.
<code>--os_distributive_path <path></code>	Specifies the path to the distribution set of your operating system.
<code>--install [-c <list_of_components>] [-u <versions>]</code>	<div> Install/upgrade the specified Parallels Virtual Automation components. </div> <div> <div> <code>-c, --components <list_of_components></code> Specifies the list of components to install. Component names should be separated by comma: <code>-c 'PVA Agent for Virtuozzo, PVA Power Panel'</code> </div> <div> <code>-u, --update <version></code> Specifies the version to which you want to upgrade. Note: The update mechanism is still in development. </div> </div>

<code>--list</code>	Prints a list of updates and components you can install on the given computer.
<code>--uninstall</code>	Removes Parallels Virtual Automation and all its components.

CHAPTER 4

Removing Parallels Virtual Automation Components

In This Chapter

Removing From Parallels Server Bare Metal Computer	57
Removing From Windows-based Computer.....	58
Removing From Linux-based Computer	59

Removing From Parallels Server Bare Metal Computer

You can remove any of the PVA components from a given computer using either the TUI wizard, or command-line options.

To remove Parallels Virtual Automation with the TUI wizard, do the following:

- 1 Log in as a user with root privileges.
- 2 Go down to the installation files directory and run `pva-setup`.
- 3 The first window provides information about the current configuration settings. To change the configuration, click **Configure**.
- 4 In the next window, select the **Uninstall** option and click **Next**.
The installer removes Parallels Virtual Automation and all its components.

To remove Parallels Virtual Automation using command line, do the following:

- 1 Log in as a user with root privileges.
- 2 Go down to the installation files directory and enter the following:

```
# ./pva-setup --uninstall
```

Note. Unlike the `install` command, the `uninstall` command doesn't require any options and removes all PVA components from the given computer.

Removing From Windows-based Computer

You can remove any of the Parallels Virtual Automation components from a given computer using either the GUI wizard, or the command-line options.

To remove Parallels Virtual Automation with the wizard, do the following:

- 1 Log in as Administrator.
- 2 Go down to the installation files directory and open `pva-setup-gui.exe` to start the installation wizard.
- 3 In the Welcome window, click **Next** to proceed to the next step.
- 4 In the next window, select **Uninstall** and click **Next**.
The installer removes Parallels Virtual Automation and all its components.

To remove Parallels Virtual Automation using command line, do the following:

- 1 Log in as Administrator.
- 2 Go down to the installation files directory and enter the following:

```
>pva-setup.exe --uninstall
```

Note: Unlike the `install` command, the `uninstall` command doesn't require any options and removes all PVA components from the given computer.

Removing From Linux-based Computer

You can remove any of the Parallels Virtual Automation components from a given computer using either the TUI wizard, or command-line options.

To remove Parallels Virtual Automation with the TUI wizard, do the following:

- 1 Log in as a user with root privileges.
- 2 Go down to the installation files directory and run `pva-setup`.
- 3 The first window provides information about the current configuration settings. To change the configuration, click **Configure**.
- 4 In the next window, select the **Uninstall** option and click **Next**.
The installer removes Parallels Virtual Automation and all its components.

To remove Parallels Virtual Automation using command line, do the following:

- 1 Log in as a user with root privileges.
- 2 Go down to the installation files directory and enter the following:

```
# ./pva-setup --uninstall
```

Note. Unlike the `install` command, the `uninstall` command doesn't require any options and removes all Parallels Virtual Automation components from the given computer.

Glossary

Application template is a template used to install a set of applications on virtual environments. See also **Template**.

Container is a virtual private server, which is functionally identical to an isolated standalone server, with its own IP addresses, processes, files, its own users database, its own configuration files, applications, system libraries, and so on. Containers on one and the same **physical server** (or **Hardware node**) share one OS kernel. However, they are isolated from each other.

EZ template is built up from separate chunks of code that are uploaded from the web every time you pick an EZ template to install in the Container. This means, that an EZ template is not an independent package but rather a unit containing all the necessary information about repositories from where the necessary packages will be uploaded to the physical server.

Hardware Node is a **physical server** where the Parallels software is installed for hosting virtual environments. The **Hardware Node** term is used in the product interface, while in technical documentation, you will find the term **physical server**.

Hardware Virtualization, or hypervisor, virtualizes at the hardware level creating a duplicate of all system resources such as operating system, CPU, memory and configuration files.

Host Operating System (or **Host OS**) is an operating system installed on the **physical server**.

Master Server is a physical server where the Parallels Virtual Automation Management Server component is installed.

OS template (or **Operating System template**) is used to create new virtual environments with a preinstalled operating system. See also **Template**.

Parallels Virtual Automation is a tool designed for managing **physical server** and all virtual environments residing on them with the help of a standard Web browser on any platform.

Parallels Power Panel is an easy-to-use web-based tool designed for administering single personal virtual environment. With Power Panel, a user with administrative access to a virtual environment can easily perform many critical management tasks, while not requiring access rights to the physical server:

Parallels Virtuozzo Containers (or **Parallels Containers**) is a complete server automation and software virtualization solution allowing you to create multiple isolated **Containers** on a single physical server to share hardware, licenses, and management effort with maximum efficiency.

Software Virtualization, in Parallels Virtual Automation documentation, stands for the Parallels software virtualization products, such as Parallels Virtuozzo Containers for Linux and Windows, Parallels Server Bare Metal, etc.

SSH stands for Secure Shell. It is a protocol for logging into a remote physical server or virtual environment and executing commands.

Standard template is a solid bundle of all the necessary template files together with the Virtuozzo virtual environments software. If newer versions of any of these packages appear, a standard template can be correspondingly updated.

TCP (TCP/IP) stands for Transmission Control Protocol/Internet Protocol. This suite of communications protocols is used to connect hosting physical servers on the Internet.

Template (or package set) is a set of original application files (packages) repackaged for mounting over Parallels File System. There are two types of templates. OS Templates are used to create new virtual environments with a preinstalled operating system. Application templates are used to install an application or a set of applications on virtual environments.

Parallels Containers and Parallels Server license is a special license that you should install on the **Hardware Node** to be able to start using the virtual environments software. Every **Hardware Node** shall have its own unique Server license.

Virtual Machine is an emulation of a physical computer by means of Parallels Server virtualization technology. It is functionally identical to an isolated standalone server. A virtual machine has its own virtual hardware and requires an operating system to control its hardware. The installed operating system and its applications are isolated inside the virtual machine and share physical hardware resources of the physical server where the virtual machine resides.

Virtual Environment is a generic name for virtual machines and Containers.

Index

A

About This Guide • 5

C

Configuring Installation Settings • 27, 31, 34

D

Documentation Conventions • 6

F

Feedback • 8

G

Getting Help • 7

Glossary • 60

H

Hardware Requirements • 16, 20, 23

I

Installing on Linux-based Computers • 31

Installing on Parallels Server Bare Metal
Computers • 24

Installing on Windows-based Computers • 28

Installing Parallels Virtual Automation Using
Autoinstaller • 24

Installing Parallels Virtual Automation via
Installation Archive • 36

Installing PVA on Container via Autoinstaller
• 35

Installing PVA on Linux-based Physical
Servers • 48

Installing PVA on Parallels Server Bare Metal
Computers • 36

Installing PVA on Windows-based Physical
Servers • 42

Introduction • 5

L

Linux Computers • 21

M

Management Server and Control Center • 36,
42, 49

O

Organization of This Guide • 6

P

Parallels Licensing Policy • 23

Parallels Server Bare Metal Computers • 15

Parallels Virtual Automation Components • 10

Parallels Virtual Automation Overview • 9

Parallels Virtual Automation System
Requirements • 15

Planning Your Parallels Virtual Automation
Management System • 12

PVA Agent for Virtuozzo and Power Panel •
45, 52

PVA Agents for Parallels Server and
Virtuozzo, Power Panel • 40

R

Removing From Linux-based Computer • 59

Removing From Parallels Server Bare Metal
Computer • 57

Removing From Windows-based Computer •
58

Removing Parallels Virtual Automation
Components • 57

S

Software Requirements • 18, 22

U

Unattended installation • 44, 47, 55

Unattended Installation • 38, 41, 51

Using GUI • 43, 45

Using TUI • 37, 40, 50, 53

W

Windows Computers • 17